


<b>TrueTest MPK API Specification</b>		
Version:	1.0.2	
Subject:	<i>MPK API specifications for TrueTest version 1.7. or higher.</i>	Research and Development Application Note
Contents:	14 Pages, No Disks	October 2019

## Application Note History

Application Note Name: Park TrueTest CLI API.docx  
 Title: Park TrueTest CLI API Specifications  
 Product: TT\_API.dll  
 Versions: MPK\_API 1.0.6262.17976 and higher &  
 TT\_API 1.0.6194.20809 and higher  
 Original Author: EMattson  
 Creation Date: January 2017  
 Release Date: February 2017

### Updates

Revision Date	Changes by/ Comments
2017-02-22	Added 'useLogging' argument to CloseCommunicationAndReinitializeCamera Method to match Initialize Method. Added ability for API to use WhiteListKey file.
2017-03-02	Updated JSON object key values so user knows how to parse.
2017-05-22	Updated GetSerialNumber method and Initialization <i>showFeedbackUI</i> parameter description.
2017-07-13	Updated CreateMeasurementSetup method to use additional arguments.
2017-08-17	Added GetLastMeshData and GetRawData methods to API
2019-10-03	New MPK API Documentation – Evan Atchison

INFORMATION PROVIDED IN THIS DOCUMENT AND ANY SOFTWARE THAT MAY ACCOMPANY THIS DOCUMENT (collectively referred to as an Application Note) IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE IMPLIED WARRANTIES OF MERCHANTABILITY AND/OR FITNESS FOR A PARTICULAR PURPOSE. The user assumes the entire risk as to the accuracy and the use of this Application Note.

Copyright © 1993-2017 Radiant Vision Systems, LLC. All Rights Reserved. Windows and Word are registered trademarks of Microsoft Corporation.  
ProMetric is a registered trademark of Radiant Vision Systems, LLC.

## Table of Contents

MPK_API Class - General .....	4
Background .....	4
Public Methods .....	4
InitializeCamera Method .....	4
GetCameraSerial Method .....	4
EquipmentReady Method .....	4
CloseCommunication Method .....	5
CloseCommunicationAndReinitializeCamera Method .....	5
GetTrueTestApiVersionInfo Method .....	5
GetMpkApiVersionInfo Method .....	5
Sequence .....	7
Public Methods .....	7
SetSequence Method .....	7
RunAllSequenceSteps .....	7
RunSequenceStepByName .....	8
RunSequenceStepListByName .....	9
Data Export .....	10
Public Methods .....	10
ExportMeasurement Method .....	10
Measurement Database .....	11
Public Methods .....	11
SetMeasurementDatabase Method .....	11
CreateMeasurementDatabase Method .....	11
GetMeasurementList .....	11
GetMeasurementInfo Method .....	12
EditMeasurementInfo Method .....	12
MPK_API Class – Measurement .....	13
Public Methods .....	13
CaptureMeasurementWithPattern Method .....	13
GetListOfPatternSetups Method .....	13
Appendix I .....	14
White List Key file .....	14

## MPK\_API Class - General

### Background

General functions to initialize the camera and retrieve the camera serial number.

### Public Methods

#### InitializeCamera Method

*Initializes camera and components of TrueTest.*

##### Syntax

###### Declaration

```
public string InitializeCamera(string cameraSerial, bool showFeedbackUI, bool useLogging)
```

###### Parameters

###### *cameraSerial*

The camera serial string to initialize. If the serial is "Demo," then use demo camera.

###### *showFeedbackUI*

If true, show windows and forms while initializing API / during take measurement. If false this will hide any camera status forms and will also hide lower level message boxes that may appear.

###### *useLogging*

If true, write to debug log while initializing API.

###### Returns

A JSON format string: {"ErrorCode": "Success = 0 | Unknown = 1 | InitializationFailure = 2"}

#### GetCameraSerial Method

*Returns the attached camera's serial number.*

##### Syntax

###### Declaration Public Function

```
GetCameraSerial() As JObject
```

###### Parameters

###### *None*

###### Returns

A JSON object. If no camera is attached or powered on, JSON value = "NONE." If exception occurred, return is JSONUnknownException. {"CameraSerial": "NONE | *CameraSerialString*"}

If return value is "NONE" then the user should NOT proceed with the camera initialization; otherwise, the camera discovery dialog window will appear.

#### EquipmentReady Method

*Returns whether camera has initialized or not.*

##### Syntax

###### Declaration Public Function

```
EquipmentReady() As JObject
```

###### Parameters

###### *None*

**Returns** A JSON object: {"ErrorCode": "Success = 0 | Unknown = 1 | InitializationFailure = 2"}

### CloseCommunication Method

*Shuts down API objects and communication to camera.*

#### Syntax

**Declaration** Public Function

CloseCommunication() As JObject

**Parameters**

*None*

**Returns** A JSON object: {"ErrorCode": "Success = 0 | Unknown = 1 | InitializationFailure = 2"}

### CloseCommunicationAndReinitializeCamera Method

*Shuts down API objects and communication to camera, then reinitializes connection and communication.*

#### Syntax

**Declaration**

Public Function CloseCommunicationAndReinitializeCamera(cameraSerial as String, showFeedbackUI As Boolean, useLogging as Boolean) As JObject

**Parameters**

*cameraSerial*

The camera serial string to initialize.

*showFeedbackUI*

If true, show windows and forms while initializing API / during take measurement.

*useLogging*

If true, write to debug log while initializing API.

**Returns**

A JSON object: {"ErrorCode": "Success = 0 | Unknown = 1 | InitializationFailure = 2"}

### GetTrueTestApiVersionInfo Method

*Returns current version of TrueTestEngine DLL.*

#### Syntax

**Declaration** Public Function

GetTrueTestApiVersionInfo As JObject

**Parameters**

*none*

**Returns**

A JSON object: {"TrueTestApiVersioninfo": "VersionInfo"} or {"ErrorCode": Unknown = 1 | InitializationFailure = 2"}. If success, version returns as File Description + Product Version (major revision.minor version.build number.revision number).

### GetMpkApiVersionInfo Method

*Returns current version of MPK\_API DLL.*

#### Syntax

**Declaration** Public Function

GetMpkApiVersionInfo As JObject

## Parameters

*none*

## Returns

A JSON object: {"MpkApiVersionInfo": "VersionInfo"} or {"ErrorCode": Unknown = 1 | InitializationFailure = 2}. If success, version returns as: File Description + Product Version (major revision.minor version.build number.revision number).

## Sequence

Functions related to preparing and running a pre-defined TrueTest sequence.

### Public Methods

#### SetSequence Method

*Sets the sequence file.*

##### Syntax

##### Declaration

```
public string SetSequence(string sequenceFilePath)
```

##### Parameters

*sequenceFilePath*

Full file path of the target sequence file.

##### Returns

JSON formatted string Success or error message.

#### RunAllSequenceSteps

*Returns the last sequence run results as a list of string.*

##### Syntax

##### Declaration

```
public string RunAllSequenceSteps(bool useCamera = true, bool saveImages = true)
```

##### Parameters

*useCamera (Optional)*

Whether to use the camera to take a new image for the sequence or to use measurements currently in the database. Defaults to true. If the software is in Demo mode without a camera, this will always be false.

*saveImages(Optional)*

Whether to save the camera measurements to a database. If useCamera is set to false, will always be set to false.

##### Returns

JSON Serialized string that deserializes to a Dictionary of List of Dictionaries containing analysis results.

The top-level dictionary is keyed by analysis name, and then has a value that is a list of results reported for that analysis.

Each result in the result list is a dictionary that has a key which is the result property name and the result property value. The available result property names are:

- *Analysis ID:* Identifying number for the analysis generating the result
- *Analysis Name:* Username of the analysis used
- *DateTime:* Time the result was generated
- *Name:* Name of the result
- *PassFail:* If the result has a Pass/Fail criteria, outputs whether it passes or fails
- *PatternName:* Name of the Pattern the Analysis ran on.

- *SequenceName*: Name of the Sequence the Analysis is contained in
- *SerialNumber*: Serial Number of the Measurement the Analysis ran on
- *Unit*: Unit of the result, if applicable
- *Value*: Value of the result, if applicable
- *ValueString*: String value of the result, if applicable

Example return:

```
{'Particle Defects': [  
  {  
    'AnalysisID': 22,  
    'AnalysisName': 'Particle Defects',  
    'DateTime': '2012-02-16T14:54:43',  
    'Name': 'NumDarkParticles',  
    'PassFail': 1,  
    'PatternName': 'White',  
    'SequenceName': 'ConoscopeTest',  
    'SerialID': 8,  
    'SerialNumber': 'Demo',  
    'Value': 0.0,  
    'ValueString': '0'  
  },  
  {  
    'AnalysisID': 22,  
    'AnalysisName': 'Particle Defects',  
    'DateTime': '2012-02-16T14:54:43',  
    'Name': 'NumDarkBlobs',  
    'PassFail': 1,  
    'PatternName': 'White',  
    'SequenceName': 'ConoscopeTest',  
    'SerialID': 8,  
    'SerialNumber': 'Demo',  
    'Value': 0.0,  
    'ValueString': '0'  
  },  
]
```

## RunSequenceStepByName

*Returns the last sequence run results as a list of string.*

### Syntax

### Declaration

```
public string RunSequenceStepByName(string stepName, bool useCamera = true, bool  
    saveImages = true)
```

### Parameters

#### *stepName*

Username of the analysis to run.



### *useCamera (Optional)*

Whether to use the camera to take a new image for the sequence or to use measurements currently in the database. Defaults to true. If the software is in Demo mode without a camera, this will always be false.

### *saveImages(Optional)*

Whether to save the camera measurements to a database. If useCamera is set to false, will always be set to false.

### Returns

Same return as RunAllSequenceSteps.

## RunSequenceStepListByName

*Returns the last sequence run results as a list of string.*

### Syntax

### Declaration

```
public string RunSequenceStepByName(List<string> stepNames, bool useCamera = true, bool  
    saveImages = true)
```

### Parameters

#### *stepName*

Username of the analysis to run.

### *useCamera (Optional)*

Whether to use the camera to take a new image for the sequence or to use measurements currently in the database. Defaults to true. If the software is in Demo mode without a camera, this will always be false.

### *saveImages(Optional)*

Whether to save the camera measurements to a database. If useCamera is set to false, will always be set to false.

### Returns

Same return as RunAllSequenceSteps.

## Data Export

Functions to export measurement data to disk.

### Public Methods

#### ExportMeasurement Method

*Exports the luminance and color data to a file for the given image key.*

#### Syntax

##### Declaration

```
public string ExportMeasurement(string imageHandle, string path, string fileName = "",  
int resolutionX = 0, int resolutionY = 0)
```

##### Parameters

###### *imageHandle*

The name or database ID of the measurement that was captured.

###### *path*

The folder location where the exported data will be written.

###### *filename (Optional)*

The name of the export file. If the name includes one of the extensions { .csv, .png, .jpg, .bmp } that extension will be used. Otherwise, the export will default to .csv. If no *filename* is passed in, a default name will be created and exported as .csv.

###### *resolutionX (Optional)*

Resolution of export in the X direction for .csv export. If none, full size image will be exported (this takes a long time).

###### *resolutionY (Optional)*

Resolution of export in the Y direction for .csv export. If none, full size image will be exported (this takes a long time).

#### Returns

A JSON string with the filepath of the exported measurement or an error message.

## Measurement Database

Functions related to setting calibrations and creating a measurement setup used during image capture.

### Public Methods

#### SetMeasurementDatabase Method

*Sets which measurementDatabase to use.*

##### Syntax

##### Declaration

```
public string SetMeasurementDatabase(string databasePath)
```

##### Parameters

##### *databasePath*

The full file path to the database

##### Returns

Json string of the database path or error message.

#### CreateMeasurementDatabase Method

*Creates a new measurementDatabase to use.*

##### Syntax

##### Declaration

```
public string CreateMeasurementDatabase(string databasePath)
```

##### Parameters

##### *databasePath*

The full file path to the database

##### Returns

Json string of the database path or error message (will throw error if database already exists).

#### GetMeasurementList

*Gets a list of measurements and some relevant information.*

##### Syntax

##### Declaration

```
public string GetMeasurementList()
```

##### Parameters

*None*

##### Returns

A JSON string that deserializes to a List of Dictionaries. Each Dictionary in the List corresponds to one measurement in the database. Each Dictionary has four keys:

- *Description:* Measurement name.

- *Measurement ID*: Unique ID of the measurement.
- *Measurement Setup*: Name of the measurement setup.
- *Pattern*: Name of the measurement pattern.

### GetMeasurementInfo Method

*Returns the color calibrations.*

Syntax

Declaration

```
public string GetMeasurementInfo(string measurementName)
```

Parameters

*measurementName*

Name or Database ID of a measurement to look for.

Returns

JSON Serialized Dictionary containing many properties of the specified measurement.

### EditMeasurementInfo Method

*Returns the image scale calibrations.*

Syntax

Declaration

```
public string EditMeasurementInfo(string measurementName, string JsonMeasInfo)
```

Parameters

*measurementName*

Name or Database ID of a measurement to look for.

*JsonMeasInfo*

JSON formatted string that must deserialize into a Dictionary<string, string>. The available dictionary keys are:

- "Description" : the serial number of the measurement
- "Model Number" : the sequence used to take the measurement
- "Technician" : the Analysis used to take the measurement
- "Pattern" : Pattern Name
- "Measurement Setup" : Measurement setup name

The value of each key will be set to the corresponding property of the designated

Returns

A JSON serialized string of a success or error message.

## MPK\_API Class – Measurement

### Background

Functions related to capturing measurements.

### Public Methods

#### CaptureMeasurementWithPattern Method

*Captures a measurement using a pre-defined pattern setup and stores it in the measurement database.*

##### Syntax

##### Declaration

```
public string CaptureMeasurementWithPattern(string patternSetupName, string measurementName)
```

##### Parameters

*patternSetupName*

The name of the pattern setup.

*measurementName*

The name of the measurement in the database.

##### Returns

A JSON string indicating if the measurement capture succeeded or failed.

#### GetListOfPatternSetups Method

*Get the current image key names stored in memory.*

##### Syntax

##### Declaration

```
public string GetListOfPatternSetups()
```

##### Parameters

*None*

##### Returns

JSON string that deserializes to a list of strings of the pattern setup names.

## Appendix I

### White List Key file

The ability to use a white list key file – to allow TrueTest to run without a dongle attached – has been added for MPK\_API version > 1.0.6262.17976 and TrueTestEngine version > 1.2.0.1136.

The WhiteListSecurity.xml file must be in the \Radiant Vision Systems Data\TrueTest\AppData folder.

As of this current writing, February 23, 2017, Radiant Imaging Colorimeters and Photometers still require the entry of the PMEngine license code *if and only if*:

1. The PMEngine license code hasn't been previously entered for a particular camera purchased before 2017/02/23.
2. If the camera calibration database (.calx) for a camera, that was used on a system and that contains the entered PMEngine license code, is not moved to the new system where the camera is being used.
  - a. If the calibration file is new, meaning it was copied from the camera, and the camera was received before the date listed above, a message box will appear requiring the user to enter the PMEngine license code.
  - b. To avoid the PMEngine license code pop-up, the user shall copy the previously used calx camera calibration file to the new machine, or use a local (network) location that houses all calx camera calibration files.

For cameras purchased *after* the listed date above: the user will not be required to enter a PMEngine license code.